

Agisoft PhotoScan User Manual

Standard Edition, Version 0.8.5

Agisoft PhotoScan User Manual: Standard Edition, Version 0.8.5

Publication date 2012

Copyright © 2012 AgiSoft LLC

Table of Contents

Overview	iv
How it works	iv
About the manual	iv
1. Installation	1
System requirements	1
OpenCL acceleration	1
Installation procedure	2
Restrictions of the trial mode	2
2. Capturing photos	3
Basic rules	3
Capturing scenarios	3
Restrictions	4
3. General workflow	6
Loading photos	6
Aligning photos	7
Building model geometry	8
Building model texture	9
Saving intermediate results	11
Exporting results	11
4. Advanced use	14
Splitting project	14
Camera calibration	16
Using masks	18
Editing sparse point cloud	20
Editing model geometry	21
A. Graphical User Interface	24
Application Window	24
Menu Commands	26
Toolbar Buttons	29
B. Troubleshooting	32
Photo alignment succeeds, but the resulting camera positions appear to be wrong	32
Reconstructed geometry appears to be cut and some important parts are missing	32
The photos included in the project file can't be opened and operations from the Workflow menu fail	33

Overview

Agisoft PhotoScan is an advanced image-based 3D modeling solution aimed at creating professional quality 3D content from still images. Based on the latest multi-view 3D reconstruction technology, it operates with arbitrary images and is efficient in both controlled and uncontrolled conditions. Photos can be taken from any position, providing that the object to be reconstructed is visible on at least two photos. Both image alignment and 3D model reconstruction are fully automated.

How it works

Generally the final goal of photographs processing by PhotoScan is to build a textured 3D model. The procedure of photographs processing and 3D model construction comprises three main stages.

1. The first stage is photographs alignment. At this stage PhotoScan searches for common points on photographs and matches them, as well as it finds the position of the camera for each picture and refines camera calibration parameters. As a result a sparse point cloud and a set of camera positions are formed.

The point cloud represents the results of photos alignment and will not be directly used in the further 3D model construction procedure (except for the point cloud based reconstruction method). However it can be exported for further usage in external programs. For instance, the point cloud model can be used in a 3D editor as a reference.

On the contrary the set of camera positions is required for further 3D model construction by PhotoScan.

2. The next stage is building geometry. Based on the estimated camera positions and pictures themselves a 3D polygon mesh, representing the object surface, is build by PhotoScan. Four algorithmic methods available in PhotoScan can be applied to 3D mesh generation: Arbitrary - Smooth, Arbitrary - Sharp, Height field - Smooth and Height field - Sharp methods. Additionally there is a Point Cloud based method for fast geometry generation based on the sparse point cloud alone.

Having built the mesh, it may be necessary to edit it. Some corrections, such as mesh decimation, removal of detached components, closing of holes in the mesh, etc. can be performed by PhotoScan. For more complex editing you have to engage external 3D editor tools. PhotoScan allows to export the mesh, edit it by another software and import it back.

3. After the geometry (i.e. the mesh) is constructed, it can be textured and / or used for orthophoto generation. Several texturing modes are available in PhotoScan, they are described in the corresponding section of this manual.

About the manual

Basically, the sequence of actions described above covers most of the model processing needs. All these operations are carried out automatically according to the parameters set by user. Instructions on how to get through these operations and descriptions of the parameters controlling each step are explained in the corresponding sections of the [Chapter 3, General workflow](#).

In some cases, however, additional actions may be required to get the desired results. For instance, pictures taken using uncommon lenses such as fish-eyes may require preliminary calibration of optical system parameters. In some capturing scenarios masking of certain regions of the photos may be required to exclude them from the calculations. All these advanced functions are described in the [Chapter 4, Advanced use](#).

It can take up quite a long time to reconstruct a 3D model. PhotoScan allows to export obtained results and save intermediate data in a form of project files at any stage of the process. If you are not familiar with the concept of projects, its brief description is given at the end of the [Chapter 3, *General workflow*](#).

In the manual you can also find instructions on the PhotoScan installation procedure and basic rules for taking "good" photographs, i.e. pictures that provide most necessary information for 3D reconstruction.

Chapter 1. Installation

System requirements

Minimal configuration

- Windows XP or later (32 or 64 bit), Mac OS X Snow Leopard or later, Debian / Ubuntu (64 bit)
- Intel Core 2 Duo processor or equivalent
- 2GB of RAM

Recommended configuration

- Windows XP or later (64 bit), Mac OS X Snow Leopard or later, Debian / Ubuntu (64 bit)
- Intel Core i7 processor
- 12GB of RAM

The number of photos that can be processed by PhotoScan depends on the available RAM and reconstruction parameters used. Assuming that a single photo resolution is of the order of 10 MPx, 2GB RAM is sufficient to make a model based on 20 to 30 photos. 12GB RAM will allow to process up to 200-300 photographs.

OpenCL acceleration

PhotoScan supports accelerated geometry reconstruction due to exploiting of the graphics hardware (GPU).

NVidia

GeForce 8xxx series and later.

ATI

Radeon HD 5xxx series and later.

PhotoScan allegedly is able to utilize processing power of any OpenCL enabled device, provided that OpenCL drivers for the device are properly installed. However, due to the large number of various combinations of video chips, driver versions and operating systems, we are unable to test and guarantee PhotoScan's compatibility with every device and on every platform.

The table below lists currently supported devices (on Windows platform only). We will pay particular attention to possible problems with PhotoScan running on these devices.

Table 1.1. Supported Desktop GPUs on Windows platform

NVIDIA	AMD
GeForce GTX 580	Radeon HD 7970
GeForce GTX 570	Radeon HD 6970
GeForce GTX 560	Radeon HD 6950
GeForce GTX 480	Radeon HD 6870

NVIDIA

GeForce GTX 470
GeForce GTX 465
GeForce GTX 285
GeForce GTX 280

AMD

Radeon HD 5870
Radeon HD 5850
Radeon HD 5830

Although PhotoScan is supposed to be able to utilize other GPU models and on other operating systems than Windows, we do not guarantee that it will work correctly.

**Note**

- OpenCL acceleration can be enabled using OpenCL tab in the Preferences dialog box.
- Using OpenCL acceleration with mobile video chips is not recommended because of the low performance of mobile GPUs.

Installation procedure

Installing PhotoScan on Microsoft Windows

To install PhotoScan on Microsoft Windows simply run the downloaded msi file and follow the instructions.

Installing PhotoScan on Mac OS X

Open the downloaded dmg image and drag PhotoScan application to the desired location on your hard drive.

Installing PhotoScan on Debian/Ubuntu

Unpack the downloaded archive with a program distribution kit to the desired location on your hard drive. Start PhotoScan by running `photoscan.sh` script from the program folder.

Restrictions of the trial mode

Once PhotoScan is downloaded and installed on your computer you can run it either in the trial mode or in the full function mode. At every run until you enter a serial number it will show a registration box offering two options: (1) use PhotoScan in the trial mode or (2) enter the serial number to confirm the purchase. The first choice is set by default, so if you are still exploring PhotoScan click the Continue button and PhotoScan will start in the trial mode.

The employment of PhotoScan in the trial mode is not time limited. Several functions, however, are not available in the trial mode. These functions are the following:

- saving the project;
- exporting reconstruction results (you can only view a 3D model on the screen)

To use PhotoScan in the full function mode you have to purchase it. On purchasing you will get the serial number to enter into the registration box on starting PhotoScan. Once the serial number is entered the registration box will not appear again and you will get full access to all functions of the program.

Chapter 2. Capturing photos

Before loading your photographs into PhotoScan you need to take them and select those suitable for 3D model reconstruction.


Photographs can be taken by any standard digital camera, as long as you follow some specific capturing guidelines. This section explains the general principles of taking and selecting pictures that provide the most appropriate data for 3D model generation.



Basic rules

- Use a digital camera with reasonably high resolution (5 MPix or more).
- Wide angle lenses suit better for reconstructing spatial relations between objects than telephoto ones.
- Avoid not textured and flat objects or scenes.
- Avoid shiny and transparent objects.
- Avoid unwanted foregrounds and moving objects as much as possible.
- Shoot shiny objects under a cloudy sky.
- Shoot pictures of the scene with a lot of overlap.
- Capture most important scene content from multiple viewpoints (3 or more).
- Do not crop or geometrically transform the images.
- More photos is better than not enough.
- Spending some time planning your shot might be very useful.
- Make sure to study the following schemes and read the list of restrictions before you get out for shooting photographs.

Capturing scenarios

The following figures represent several typical capturing scenarios:





Restrictions

In some cases it might be very difficult or even impossible to build a correct 3D model from a set of pictures. A short list of typical reasons for photographs unsuitability is given below.

Modifications of photographs

PhotoScan can process only unmodified photos as they were taken by a digital photo camera. Processing the photos which were manually cropped or geometrically warped is likely to fail or produce highly inaccurate results. Photometric modifications do not affect reconstruction results.

Lack of EXIF data

To estimate the field of view for each photo PhotoScan uses the information saved in the EXIF part of each picture. If EXIF data are available you can expect to get the best possible 3D reconstruction. However 3D scene can also be reconstructed in the absence of EXIF data. In this case PhotoScan assumes that the 35mm focal length equivalent equals to 50 mm and tries to align the photos in accordance with this assumption. If the correct focal length value differs significantly from 50 mm, the alignment can give incorrect results or even fail. In such cases it is required to specify initial camera calibration manually.

The details of necessary EXIF tags and instructions for manual setting of the calibration parameters are given in the [Camera calibration](#) section

Lens distortion

The distortion of the lens being used to capture the photos should be well modeled using the Brown's distortion model. Otherwise it is almost impossible to build a precise 3D model. Fish eyes and ultra-wide angle lenses are poorly modeled by the distortion model implemented, which leads to inaccurate reconstructions.

Chapter 3. General workflow

The processing of images by PhotoScan includes the following main steps:

- loading photos into PhotoScan;
- inspecting loaded images, removing unnecessary images;
- aligning photos;
- building 3D model;
- editing 3D model;
- exporting results.


If you are using PhotoScan in the full function (not the trial) mode, intermediate results of the image processing can be saved at any stage in the form of project files and can be used later. The concept of projects and project files is briefly explained in the [Saving intermediate results](#) section.

The list above represents all the necessary steps involved in the construction of a textured 3D model from your photos. Some additional tools, which you may find to be useful, are described in the [Chapter 4, Advanced use](#).

Loading photos

Before starting any operation it is necessary to point out what photos will be used as a source for 3D reconstruction. In fact, photographs themselves are not loaded into PhotoScan until they are needed. So, when you "load photos" you only indicate photographs that will be used for further processing.

To load a set of photos

1. Select Add Photos... command from the Workflow menu or click  Add Photos toolbar button.
2. In the Add Photos dialog box browse to the folder containing the images and select files to be processed. Then click Open button.
3. Selected photos will appear on the Workspace pane.


Note

- PhotoScan accepts the following image formats: JPEG, TIFF, PNG, BMP, PPM and JPEG Multi-Picture Format (MPO). Photos in any other format will not be shown in the Add Photos dialog box. To work with such photos you will need to convert them in one of the supported formats.

If you have loaded some unwanted photos, you can easily remove them at any moment.

To remove unwanted photos

1. On the Workspace pane select the photos to be removed.

2. Right-click on the selected photos and choose Remove Items command from the opened context menu, or click  Remove Items toolbar button. The selected photos will be removed from the working set.

Inspecting the loaded photos

Loaded photos are displayed on the Workspace pane along with flags reflecting their status.

The following flags can appear next to the photo name:

NC (Not calibrated)

Notifies that the EXIF data available is not sufficient to estimate the camera focal length. In this case PhotoScan assumes that the corresponding photo was taken using 50mm lens (35mm film equivalent). If the actual focal length differs significantly from this value, manual calibration may be required. More details on manual camera calibration can be found in the [Camera calibration](#) section.

NA (Not aligned)

Notifies that external camera orientation parameters were not estimated for the current photo yet.

Images loaded to PhotoScan will not be aligned until you perform the next step - photos alignment.

Aligning photos

Once photos are loaded into PhotoScan, they need to be aligned. At this stage PhotoScan finds the camera position for each photo and builds a point cloud model.

To align a set of photos

1. Select Align Photos... command from the Workflow menu.
2. In the Align Photos dialog box select the desired alignment options. Click OK button when done.
3. The progress dialog box will appear displaying the current processing status. To cancel processing click Cancel button.

Alignment having been complete, computed camera positions and a sparse point cloud will be displayed. You can inspect alignment results and remove incorrectly positioned photos, if any. To see the matches between any two photos use View Matches... command from the Tools menu.

The point cloud and estimated camera positions can be exported for processing with another software if needed.

Incorrectly positioned photos can be realigned.

To realign a subset of photos

1. Reset alignment for incorrectly positioned photos using Reset Photo Alignment command from the photo context menu.
2. Select photos to be realigned and use Align Selected Photos command from the photo context menu.
3. The progress dialog box will appear displaying the current processing status. To cancel processing click Cancel button.

Alignment parameters

The following parameters control the photo alignment procedure and can be modified in the Align Photos dialog box:

Accuracy

Higher accuracy setting helps to obtain more accurate camera position estimates. Lower accuracy setting can be used to get the rough camera positions in a shorter period of time.

Pair preselection

The alignment process of large photo sets can take a long time. A significant portion of this time period is spent on matching of detected features across the photos. Image pair preselection option may speed up this process due to selection of a subset of image pairs to be matched. In the `Generic` preselection mode the overlapping pairs of photos are selected by matching photos using lower accuracy setting first.



Constrain features by mask

When this option is enabled, features detected in the masked image regions are discarded. For additional information on the usage of masks please refer to the [Using masks](#) section.

Building model geometry

3D model reconstruction is a computationally intensive operation and can take a long time, depending on the quantity and resolution of loaded photos. It is recommended to build a model with the lowest quality first to estimate the applicability of the chosen reconstruction method, and then to recompute the results using a higher quality setting. It is also recommended to save the project before building the geometry.

To build a 3D model

1. Check the reconstruction volume bounding box. To adjust the bounding box use the  `Resize Region` and  `Rotate Region` toolbar buttons. Rotate the bounding box and then drag corners of the box to the desired positions. If the `Height` field reconstruction method is applied, the red side of the bounding box will define the reconstruction plane. In this case make sure that the bounding box is correctly oriented.
2. Select the `Build Geometry...` command from the Workflow menu.
3. In the Build Geometry dialog box select the desired reconstruction parameters. Click OK button when done.
4. The progress dialog box will appear displaying the current processing status. To cancel processing click Cancel button.

Reconstruction methods

Agisoft PhotoScan supports several reconstruction methods and settings, which help to produce optimal reconstructions for a given data set.

Object type

Arbitrary

`Arbitrary` object type can be used for modeling of any kind of object. It should be selected for closed objects, such as statues, buildings, etc. It doesn't make any assumptions on the type of the object modeled, which comes at a cost of higher memory consumption.

Height field

The `Height field` object type is optimized for modeling of planar surfaces, such as terrains or bas-reliefs. It should be selected for aerial photography processing as it requires lower amount of memory and allows for larger data sets processing.

Geometry type**Sharp**

`Sharp` geometry type option leads to more accurate reconstruction results and does not introduce extra geometry, like hole filling "patches". Manual hole filling is usually required at the post processing step.

Smooth

`Smooth` geometry type option produces watertight reconstructions with no or little holes on resulting surface. Large areas of extra geometry might be generated with this method, but they could be easily removed later using selection and cropping tools. `Smooth` setting is recommended for orthophoto generation.

Reconstruction parameters

Quality

Specifies the desired reconstruction quality. Higher quality settings can be used to obtain more detailed and accurate geometry, but require longer time for processing. `Point Cloud` quality setting is used for fast 3D model generation based solely on the sparse point cloud. The option is available for `Smooth` geometry type only.

Face count

Specifies the maximum face count in the final mesh. 0 - if no decimation is required.

Filter threshold

Specifies the maximum face count of small connected components to be removed after surface reconstruction (in percent of the total face count). The 0 value disables connected component filtering.

Hole threshold (Height field methods only)

Specifies the maximum size of holes to be filled after surface reconstruction (in percent of the total surface area). The 0 value disables automatic hole filling.

**Note**

- PhotoScan tends to produce 3D models with excessive geometry resolution, so it is recommended to perform mesh decimation after geometry computation. More information on mesh decimation and other 3D model geometry editing tools is given in the [Editing model geometry](#) section.

Building model texture

To generate 3D model texture

1. Select `Build Texture...` command from the `Workflow` menu.
2. Select the desired texture generation parameters in the `Build Texture` dialog box. Click `OK` button when done.
3. The progress dialog box will appear displaying the current processing status. To cancel processing click `Cancel` button.

Texture mapping modes

The texture mapping mode determines how the object texture will be packed in the texture atlas. Proper texture mapping mode selection helps to obtain optimal texture packing and, consequently, better visual quality of the final model.

Generic

The default mode is the `Generic` mapping mode; it allows to parameterize texture atlas for arbitrary geometry. No assumptions regarding the type of the scene to be processed are made; program tries to create as uniform texture as possible.

Adaptive orthophoto

In the `Adaptive orthophoto` mapping mode the object surface is split into the flat part and vertical regions. The flat part of the surface is textured using the orthographic projection, while vertical regions are textured separately to maintain accurate texture representation in such regions. When in the `Adaptive orthophoto` mapping mode, program tends to produce more compact texture representation for nearly planar scenes, while maintaining good texture quality for vertical surfaces, such as walls of the buildings.

Orthophoto

In the `Orthophoto` mapping mode the whole object surface is textured in the orthographic projection. The `Orthophoto` mapping mode produces even more compact texture representation than the `Adaptive orthophoto` mode at the expense of texture quality in vertical regions.

Single photo

The `Single photo` mapping mode allows to generate texture from a single photo. The photo to be used for texturing can be selected from `Texture from list`.

Keep uv

The `Keep uv` mapping mode generates texture atlas using current texture parameterization. It can be used to rebuild texture atlas using different resolution or to generate the atlas for the model parametrized in the external software.

Texture generation parameters

The following parameters control various aspects of texture atlas generation:

Texture from (Single photo mapping mode only)

Specifies the photo to be used for texturing. Available only in the `Single photo` mapping mode.

Blending mode (not used in Single photo mode)

Selects the way how pixel values from different photos will be combined in the final texture.

`Average` - uses the average value of all pixels from individual photos.

`Mosaic` - gives more quality for orthophoto and texture atlas than `Average` mode, since it does not mix image details of overlapping photos but uses more appropriate photo. Mosaic texture blending mode is especially useful for orthophoto generation based on approximate geometric model.

`Max Intensity` - the photo which has maximum intensity of the corresponding pixel is selected.

`Min Intensity` - the photo which has minimum intensity of the corresponding pixel is selected.

Atlas width

Specifies the width of the texture atlas in pixels.

Atlas height

Specifies the height of the texture atlas in pixels.

Saving intermediate results

Certain stages of 3D model reconstruction can take a long time. The full chain of operations could easily last for 4-6 hours when building a model from hundreds of photos. It is not always possible to finish all the operations in one run. PhotoScan allows to save intermediate results in a project file.

PhotoScan project files may contain the following information:

- List of loaded photographs with reference paths to the image files.
- Photo alignment data such as information on camera positions, point cloud model and set of refined camera calibration parameters for each photo.
- Reconstructed 3D model with any changes made by user. This includes geometry and texture if they were built.
- Structure of the project, i.e. number of chunks in the project and their content.

You can save the project at the end of any processing stage and return to it later. To restart work simply load the corresponding file into PhotoScan. Project files can also serve as backup files or be used to save different versions of the same model.

Project files use relative paths to reference original photos. Thus, when moving or copying the project file to another location do not forget to move or copy photographs with all the folder structure involved as well. Otherwise, PhotoScan will fail to run any operation requiring source images, although the project file including the reconstructed model will be loaded up correctly.

Exporting results

PhotoScan supports export of processing results in various representations.

Point clouds and camera calibration data can be exported right after photo alignment is completed. All other export options are available after the geometry is built.

In some cases editing model geometry in the external software may be required. PhotoScan supports model export for editing in external software and then allows to import it back, as it is described in the [Editing model geometry](#) section of the manual.

Point Cloud export

To export sparse or dense point cloud

1. Select Export Points... command from the File menu.
2. Browse the destination folder, choose the file type, and print in the file name. Click Save button.
3. In the Export Points dialog box set the Point Cloud value for the Quality parameter if you need to export sparse point cloud. To export a dense point cloud choose an appropriate quality among the rest of the values.
4. Specify the coordinate system and indicate export parameters applicable to the selected file type.

5. Click OK button to start export.
6. The progress dialog box will appear displaying the current processing status. To cancel processing click Cancel button.

In some cases it may be reasonable to edit sparse point cloud before exporting it. To read about point cloud editing refer to the [Editing sparse point cloud](#) section of the manual.

PhotoScan supports point cloud export in the following formats:

- Wavefront OBJ
- Stanford PLY
- XYZ text file format (only for sparse point cloud export)
- ASPRS LAS



Note

- Saving color information of the point cloud is supported by the PLY, TXT and LAS file formats.
- Saving point normals information is supported by the OBJ, PLY and TXT file formats.

Camera calibration and positions data export

To export camera calibration and positions data select Export Cameras... command from the Tools menu.

To export / import only camera calibration data select Camera Calibration... command from the Tools menu.

PhotoScan supports camera data export in the following formats:

- PhotoScan structure file format (XML based)
- Bundler OUT file format
- CHAN file format
- Boujou TXT file format
- Omega Phi Kappa text file format



Note

- Camera data export in Bundler and Boujou file formats will save sparse point cloud data in the same file.
- Camera data export in Bundler file format would not save distortion coefficient k3.

3D model export

To export 3D model

1. Select Export Model... command from the File menu.

2. Browse the destination folder, choose the file type, and print in the file name. Click Save button.
3. In the Export Model dialog box specify the coordinate system and indicate export parameters applicable to the selected file type if needed.
4. Click OK button to start export.
5. The progress dialog box will appear displaying the current processing status. To cancel processing click Cancel button.



Note

- If the model is referenced in local coordinates, PhotoScan can write a KML file for the exported model to be correctly located on Google maps.

PhotoScan supports model export in the following formats:

- Wavefront OBJ
- 3DS file format
- VRML
- COLLADA
- Stanford PLY
- Autodesk DXF
- U3D
- Adobe PDF

Some file formats (OBJ, 3DS, VRML, COLLADA, PLY) save texture image in a separate file. The texture file should be kept in the same directory as the main file describing the geometry. If the texture atlas was not built only the model geometry is exported.

Chapter 4. Advanced use


Splitting project

In some cases it is very hard or even impossible to generate 3D model of the whole object in one go. This could happen for instance if the total amount of photographs is too large to be processed. To overcome this PhotoScan offers the possibility of splitting the set of photos in several separate "chunks" within the project. The alignment of photos, building geometry and forming the texture atlas may be performed on each chunk separately and then the resulting 3D models may be combined together.

Working with chunks is no more difficult than using PhotoScan following the general workflow. In fact, in PhotoScan always exists at least one active chunk and all the 3D model processing workflow operations are applied to this chunk.

All you need to know to work with several chunks is how to create chunks and how to combine resulting 3D models from separate chunks into one model.

Creating a chunk

To create new chunk click on the  Add Chunk toolbar button on the Workspace pane or select Add Chunk command from the Workspace context menu (available by right-clicking on the root element in the Workspace pane).

After the chunk is created you may load photos in it, align them, generate mesh surface model, build texture atlas, export the models at any stage and so on. The models in the chunks are not linked with each other.

To move photos from one chunk to another simply select them in the list of photos on the Workspace pane, and then drag and drop in the desirable chunk.

Working with chunks

All operations within the chunk are carried out following the common workflow: loading photographs, aligning them, building geometry model, building texture atlas, exporting 3D model and so on.

Note that all these operations are applied to the active chunk. When a new chunk is created it is activated automatically. Save project operation saves the content of all chunks.

To set another chunk as active

1. Right-click on the chunk title on the Workspace pane.
2. Select Set Active command from the context menu.

To remove chunk

1. Right-click on the chunk title on the Workspace pane.
2. Select Remove Items command from the context menu.

Aligning models from several chunks

After the "partial" 3D models are built in several chunks they can be merged together. Before merging the models they need to be aligned.

To align models from separate chunks

1. Select Align Chunks command from the Workflow menu.
2. In the Align Chunks dialog box select chunks to be aligned, indicate reference chunk with a double-click. Set desired alignment options. Click OK button when done.
3. The progress dialog box will appear displaying the current processing status. To cancel processing click the Cancel button.

Note

- Chunks alignment can be performed if at least two chunks contain aligned photos.

Chunks alignment parameters

The following parameters control the chunks alignment procedure and can be modified in the Align Chunks dialog box:

Method

Defines the chunks alignment method. `Point based` method aligns chunks by matching photos across the different chunks.

Accuracy (Point based alignment only)

Higher accuracy setting helps to obtain more accurate chunk alignment results. Lower accuracy setting can be used to get the rough chunk alignment in the shorter time.

Preselect image pairs (Point based alignment only)

The alignment process of many chunks may take a long time. A significant portion of this time is spent for matching of detected features across the photos. Image pair preselection option can speed up this process by selection of a subset of image pairs to be matched.

Constrain features by mask (Point based alignment only)

When this option is enabled, features detected in the masked image regions are discarded. For additional information on the usage of masks refer to the [Using masks](#) section.

Merging models from several chunks

After alignment is complete the separate models can be merged into a single model.

To merge models

1. Select Merge Chunks command from the Workflow menu.
2. In the Merge Chunks dialog box select chunks to be merged and the desired merging options. Click OK button when done.
3. PhotoScan will merge the separate chunks into one. The merged chunk will be displayed in the project content list on Workspace pane.

Chunks merging parameters

The following parameters control the chunks merging procedure and can be modified in the Merge Chunks dialog box:

Merge models

Defines if models from the selected chunks are merged.

Merge markers

Defines if markers from the selected chunks are merged (only markers with the same labels would be merged).

Chunks merging result (i.e. photos, points and geometry) will be stored in the new chunk and it may be treated as common chunk (e.g. textured and/or exported).

Batch processing

PhotoScan allows to perform general workflow operations with multiple chunks automatically. It is useful when dealing with a large number of chunks to be processed.

Batch processing can be applied to all chunks in the Workspace, to unprocessed chunks only, or to the chunks selected by the user.

Batch processing can perform the following operations:

- Align photos
- Build geometry
- Build texture
- Save project after every completed operation

To start batch processing

1. Select Batch Process... command from the Workflow menu.
2. Click Add to add the desired processing stages.
3. In the Add Job dialog select the kind of operation to be performed, the list of chunks it should be applied to, and desired processing parameters. Click OK button when done.
4. Repeat the previous steps to add other processing steps as required.
5. Click OK button to start processing.

Camera calibration

While carrying out photos alignment PhotoScan estimates both internal and external camera orientation parameters, including nonlinear radial distortions. For a successful estimation the information on approximate focal length values is required. Normally this data is extracted automatically from the EXIF metadata, or the 50mm focal length (35mm film equivalent) is assumed if the EXIF information is insufficient.

In some cases, the 50mm guess can differ too much from the actual focal length. This can lead to the failure of the alignment process. In such cases it is required to specify the initial camera calibration manually.

To specify camera calibration manually

1. Select Camera Calibration... command from the Tools menu.

2. In the Camera Calibration dialog box, select `Initial` viewing mode. Select the photos to be calibrated.
3. Modify the calibration parameters displayed in the corresponding edit boxes. Normally only `fx`, `fy`, `cx` and `cy` values should be corrected.
4. Click `Apply` button to set the calibration. You will notice that the selected photos will be marked with the `C` flag (Custom calibration).
5. Click `Close` button to close the camera calibration dialog.

Calibration parameters

fx, fy

Focal length in x- and y-dimensions measured in pixels.

cx, cy

Principal point coordinates, i.e. coordinates of lens optical axis interception with sensor plane.

skew

Skew transformation coefficient.

k1, k2, k3

Radial distortion coefficients.

p1, p2

Tangential distortion coefficients.

How to set up appropriate values

In the case of missing EXIF data or too large lens distortions manual setting of lens calibration may be required. This may happen if you used an old manual lens which cannot be detected by the camera or if the photos were taken by the film camera and digitized later. Some hints on selecting suitable calibration parameters are listed below:

- It is very unlikely that skew transformation coefficient will have non zero value. So its almost always safe to set `skew` parameter equal to zero.
- Unless you have used lenses with high distortion, such as fish eyes, the same applies to distortion coefficients. Leave it zero and PhotoScan will estimate them on its own. If ultra wide or fisheye lens were used to capture the photos you may try to estimate them using Agisoft Lens utility for lens calibration (<http://www.agisoft.ru/products/lens/>).
- `fx` and `fy` coefficients are normally equal. They may be different if the pixels of recording media were not square, which is a very rare case. If you know the focal length of the lens, physical dimension of the optical sensor and size of picture in pixels you may easily calculate these coefficients as: $fx = \text{focal length in mm} * x\text{-dimension of sensor in pixels} / x\text{-dimension of sensor in mm}$. Similar formula applies to `fy`.
- For conventional (non tilt and shift) lenses the optical axis of the lens is likely to intercept the optical sensor plane in its geometric center. So for `cx` and `cy` coefficient the coordinates of the image center would be the good guess.

Automatic refinement of camera calibration parameters

By default PhotoScan considers specified camera calibration parameters as the initial guess, and refines them later during the photo alignment. That is generally a desirable behaviour. However in the cases when

the camera calibration is known precisely (like in case of a metric camera), it may be required to protect camera calibration parameters from optimization. To fix the camera calibration parameters select the Fix calibration check box in the Camera Calibration dialog.

Using masks

Overview



Masks are used in PhotoScan to specify the areas on the photos which can otherwise be confusing to the program or lead to incorrect reconstruction results. Masks can be applied at the following stages of processing:

- Alignment of the photos
- Building 3D model geometry
- Building 3D model texture

Alignment of the photos

Masked areas can be excluded during feature point detection. Thus, the objects on the masked parts of the photos are not taken into account while estimating camera positions. This is important in the setups, where the object of interest is not static with respect to the scene, like when using a turn table to capture the photos.

Masking may be also useful when the object of interest occupies only a small part of the photo. In this case a small number of useful matches can be filtered out mistakenly as a noise among a much greater number of matches between background objects.

Building 3D model

While building the model, masked areas are not used in the surface generation process. Masking can be used to reduce the resulting model complexity, by eliminating the areas on the photos that are not of interest.

Masked areas are always excluded from processing during surface reconstruction and texture generation stages.

Let's take for instance a set of photos of some object. Along with an object itself on each photo some background areas are present. These areas may be useful for more precise camera positioning, so it is better to use them while aligning the photos. However, impact of these areas at the building geometry stage is exactly opposite. If they are used for building geometry the resulting model will contain object of interest and its background. Background geometry will "consume" some part of mesh polygons that could be otherwise used for modeling the main object.

Setting the masks for such background areas allows to avoid this problem and increases the precision and quality of geometry reconstruction.




Building texture atlas

During texture atlas generation, masked areas on the photos are not used for texturing. Masking areas on the photos that are occluded by outliers or obstacles helps to prevent the "ghosting" effect on the resulting texture atlas.

Mask editing

Masks in PhotoScan are represented by contours, bounding the certain image regions. Modification of the current mask is performed by adding or subtracting selections. A selection is created by using one of the supported selection tools and is not incorporated in the current mask until it is merged with a mask using Add Selection or Subtract Selection operations.

To edit the mask

1. Open the photo to be masked by double clicking on its name on the Workspace / Photo / Ground Control pane. The photo will be opened in the main window. The existing mask will be displayed as a shaded region on the photo.
2. Select the desired selection tool and generate a selection.
3. Click on  Add Selection toolbar button to add current selection to the mask, or  Subtract Selection to subtract the selection from the mask.  Invert Selection button allows to invert current selection prior to adding or subtracting it from the mask.

To import (export) a mask

1. Open the photo to be masked by double clicking on its name in the Workspace / Photo / Ground Control pane. The photo will be opened in the main window.
2. Select Import (Export) mask... command from Photo menu.
3. In the Import (Export) Mask dialog box select whether the mask should be imported to (exported from) the current photo only, all photos in the chunk or to (from) the entire Workspace. Click OK button when done.

If photo has alpha channel it could be applied as a mask to one or more photos in Workspace through Import mask dialog.

Supported selection tools

The following tools can be used for creating selections:

Rectangle selection tool

Rectangle selection tool is used to select large areas or to clean up the mask after other selection tools were applied.

Note

- To add new area to the current selection hold the **Ctrl** key during selection of additional area.

Intelligent scissors tool

Intelligent scissors is used to generate a selection by specifying its boundary. The boundary is formed by selecting a sequence of vertices with a mouse, which are automatically connected with segments. The segments can be formed either by straight lines, or by curved contours snapped to the object boundaries. To enable snapping, hold **Ctrl** key while selecting the next vertex. To complete the selection, the boundary should be closed by clicking on the first boundary vertex.

Intelligent paint tool

Intelligent paint tool is used to "paint" a selection by the mouse, continuously adding small image regions, bounded by object boundaries.

Magic Wand tool

Magic Wand tool is used to select uniform areas of the image. To make a selection with a Magic Wand tool, click inside the region to be selected.

The range of pixel colors selected by Magic Wand is controlled by the tolerance value. At lower tolerance values the tool selects fewer colors similar to the pixel you click with the Magic Wand tool. Higher value broadens the range of colors selected.

Note

- The masks are generated individually for each image. If some object should be masked out, it should be masked out on all photos, where that object appears.

Editing sparse point cloud

The following point cloud editing tools are available in PhotoScan:

- Reprojection error filtering
- Manual points removal

Note


- For points removal operations such as manual points removal and reprojection error filtering it is possible to undo the last point cloud editing operation. There are Undo/Redo command in the Edit menu.

Reprojection error filtering

In some cases you may need to find out where the points with high reprojection error are located within the cloud. Reprojection error filtering helps to highlight such points, which usually are supposed to be removed.

To remove points with high reprojection error





1. Switch to Point Cloud View mode using Point Cloud button from the toolbar.
2. Select Gradual Selection... command from the Edit menu.

3. In the Gradual Selection dialog box set the value of reprojection error of points to be selected using the slider. You can observe how the selection changes while dragging the slider. Click OK button to finalize the selection.
4. To remove selected points use Delete Selection command from the Edit menu or click  Delete Selection toolbar button (or simply press **Del** button on the keyboard).

Manual points removal

Points with high reprojection error can be also removed manually.

To remove points from the sparse cloud manually

1. Switch to Point Cloud View mode using Point Cloud button from the toolbar.
2. Indicate points to be deleted using  Rectangle Selection or  Circle Selection toolbar buttons. To add new points to the current selection hold the **Ctrl** key during selection of additional points. To remove some points from the current selection hold the **Shift** key during selection of points to be removed.
3. To delete selected points click the  Delete Selection toolbar button / use Delete Selection command from the Edit menu. To crop selection to the selected points click the  Crop Selection toolbar button / use Crop Selection command from the Edit menu.

Editing model geometry

The following mesh editing tools are available in PhotoScan:

- Decimation tool
- Connected component filtering
- Manual face removal

More complex editing can be done in the external 3D editing tools. PhotoScan allows to export mesh and then import it back for this purpose.

Note

- For face removal operations such as manual face removal and connected component filtering it is possible to undo the last mesh editing operation. There are Undo/Redo command in the Edit menu.

Please note that undo/redo commands are not supported for mesh decimation and this operation can not be undone.

Decimation tool

Decimation is a tool used to decrease the geometric resolution of the model by replacing high resolution mesh with a lower resolution one, which is still capable of representing the object geometry with high accuracy. PhotoScan tends to produce 3D models with excessive geometry resolution, so mesh decimation is usually a desirable step after geometry computation.

The high detailed models may contain hundreds of thousands of polygons. While it is acceptable to work with such a complex models in 3D editor tools, in most conventional tools like Adobe Reader or Google Earth high complexity of 3D models may noticeably decrease application performance. High complexity also results in longer time required to build texture and to export model in pdf file format.

In some cases it is desirable to keep as much geometry details as possible like it is needed for scientific and archive purposes. However, if there are no special requirements it is recommended to decimate the model down to 100 000 - 200 000 polygons for exporting in PDF, and to 100 000 or even less for displaying in Google Earth and alike tools.

To decimate 3D model

1. Select Decimate Mesh... command from the Tools menu.
2. In the Decimate Mesh dialog box specify the target number of faces, which should remain in the final model. Click on the OK button to start decimation.
3. The progress dialog box will appear displaying the current processing status. To cancel processing click on the Cancel button.




Note

- Texture atlas is discarded during decimation process. You will have to rebuild texture atlas after decimation is complete.

Connected component filtering

In some cases reconstructed geometry may contain the cloud of small isolated mesh fragments surrounding the "main" model. Connected component filtering helps to remove small isolated mesh fragments, which are usually reconstructed incorrectly or are not needed.

To remove small isolated mesh fragments



1. Select Gradual Selection... command from the Edit menu.
2. In the Gradual Selection dialog box select the size of isolated components to be removed using the slider. You can observe how the selection changes while dragging the slider. Click OK button to finalize the selection.
3. To remove the selected components use Delete Selection command from the Edit menu or click  Delete Selection toolbar button (or simply press Del button on the keyboard).



Note that PhotoScan always selects the fragments starting from the smallest ones. If the model contains only one component the selection will be empty.

Manual face removal

Unnecessary and excessive sections of model geometry can be also removed manually.

To remove part of the faces manually

1. Select rectangle or circle selection tool using  Rectangle Selection or  Circle Selection toolbar buttons.

2. Make the selection using the mouse. To add new faces to the current selection hold the **Ctrl** key during selection of additional faces. To remove some faces from the current selection hold the **Shift** key during selection of faces to be removed.
3. To delete selected faces click the  Delete Selection toolbar button or use Delete Selection command from the Edit menu. To crop selection to the selected faces click the  Crop Selection toolbar button or use Crop Selection command from the Edit menu.

To grow or shrink current selection

1. To grow current selection press **PageUp** key in the selection mode. To grow selection by even a larger amount, press **PageUp** while holding **Shift** key pressed.
2. To shrink current selection press **PageDown** key in the selection mode. To shrink selection by even a larger amount, press **PageDown** while holding **Shift** key pressed.

Editing mesh in the external program

To export mesh for editing in the external program

1. Select Export Model... command from the File menu.
2. In the Save As dialog box, specify the desired mesh format in the Save as type combo box. Select the file name to be used for the model and click Save button.
3. In the opened dialog box specify additional parameters specific to the selected file format. Click OK button when done.

To import edited mesh

1. Select Import Mesh... command from the Tools menu.
2. In the Open dialog box, browse to the file with the edited model and click Open.




Note

- PhotoScan supports loading models in Wavefront OBJ and Stanford PLY file formats only. Please make sure to select one of these file formats when exporting model from the external 3D editor.

Appendix A. Graphical User Interface

Application Window



General view of application window.

Model view

Model view tab is used for displaying 3D data as well as for 3D model and point cloud editing. The view of the model depends on the current processing stage and is also controlled by mode selection buttons on the PhotoScan toolbar.

Model can be shown in textured, solid, shaded, or wireframe mode. Along with the model the results of photo alignment can be displayed. These include point cloud and camera positions for each photo.

PhotoScan supports the following tools for navigation in the 3D view:

Tool	Keyboard modifier
Rotation Tool	Default
Pan Tool	Ctrl key pressed
Zooming Tool	Shift key pressed

All navigation tools are accessible in the navigation mode only. To enter the navigation mode click the



Navigation toolbar button.



Note

- Zooming into the model can be also controlled by the mouse wheel.

Photo view

Photo view tab is used for displaying individual photos as well as masks and markers on them.

Photo view is visible only if any photo is opened. To open the photo double-click on its name on the Workspace, Ground Control, or Photos pane.

Workspace pane

On the Workspace pane all elements comprising the current project are displayed. These elements can include:

- List of chunks in the project
- List of photographs in each chunk
- List of markers in each chunk
- 3D models in separate chunks

Buttons located on the pane toolbar allow:

- Add chunks
- Add photographs
- Add markers
- Enable or disable certain photographs or chunks for processing at further stages.
- Remove items

Each element in the list is linked with the context menu providing quick access to some common operations.

Photos pane

Photos pane displays the list of photos in the active chunk in the form of thumbnails.

Buttons located on the pane toolbar allow:

- Add photos

- Enable or disable certain photos or chunks for processing at further stages.
- Remove items
- Increase or decrease icons' size
- Filter photos by feature points or by markers

Console pane

Console pane is used for:

- Displaying auxiliary information
- Displaying error messages
- Python commands

Buttons located on the pane toolbar allow:

- Save log
- Clear log
- Execute Python script

Ground Control pane

Ground Control pane is designed for:

- Displaying camera and / or markers coordinates
- Displaying camera orientation
- Displaying estimation errors

Buttons located on the pane toolbar allow:

- Import / export reference coordinates
- Convert reference coordinates from one system to the other
- Indicate coordinate system and measurement accuracy to be assumed through Settings dialog
- Optimize estimation and update data
- Switch between source coordinates, estimated coordinates, and errors views



Note

- To open any pane select a corresponding command from the View menu.

Menu Commands



File Menu







New

Creates an empty PhotoScan project.









File Menu

 Open...	Opens PhotoScan project file.
Append...	Appends existing PhotoScan project file to the current one.
 Save	Saves PhotoScan project file.
Save As...	Saves PhotoScan project file with a new name.
Export Model...	Saves 3D model.
Export Points...	Saves sparse / dense point cloud.
Exit	Quits the application. Prompts to save active project.


Edit Menu

 Undo	Undo the last editing operation.
 Redo	Redo the previously undone editing operation.
 Delete Selection	Removes selected faces from the mesh or selected points from the point cloud.
 Crop Selection	Crops selected faces / points.
Invert Selection	Inverts current selection.
Grow Selection	Grows current selection.
Shrink Selection	Shrinks current selection.
Select Components...	Selects isolated mesh components.


View Menu

 Point Cloud	Displays sparse point cloud reconstructed during photo alignment.
 Shaded	Displays 3D model in the shaded mode.
 Solid	Displays 3D model in the solid mode.
 Wireframe	Displays 3D model in the wireframe mode.
 Textured	Displays 3D model in the textured mode.
 Show Cameras	Shows or hides camera positions reconstructed during image alignment.
 Show Trackball	Shows or hides the trackball.
 Show Info	Shows or hides the mesh information on-screen display.
Perspective/Orthographic	Switches visualisation view between Perspective and Orthographic.

View Menu

Workspace	Shows or hides Workspace pane.
 Ground Control	Shows or hides Grount Control pane.
Photos	Shows or hides Photos pane.
Console	Shows or hides Console pane.

Workflow Menu

 Add Photos...	Loads additional photos to be processed by PhotoScan.
Align Photos...	Generates camera positions and sparse point cloud.
Build Geometry...	Generates 3D model geometry.
Build Texture...	Generates 3D model texture.
Align Chunks	Aligns multiple chunks.
Merge Chunks	Merges multiple chunks into the single model.
Batch Process...	Opens Batch Process dialog box.

Tools Menu















Decimate Mesh...	Decimates mesh to the target face count.
Close Holes...	Closes holes on the model surface.
Import Mesh...	Imports edited mesh from the external program.
Import Texture...	Imports edited texture from the external program.
Export Texture...	Exports model texture.
View Mesh Statistics...	Collects and displays mesh statistics.
Import Cameras...	Imports camera positions and orientation data.
Export Cameras...	Exports camera positions and orientation data.
Undistort Photos...	Removes nonlinear distortions by warping source photos.
View EXIF Data...	Displays EXIF data for the photos in the active chunk.
View Matches...	Displays matches for the photos in the active chunk.
Camera Calibration...	Shows camera calibration dialog box.
Preferences...	Shows preferences dialog box.
 Run Script...	Opens Python Run Script dialog box.

Photo Menu

 Navigation	Selects navigation mode.
 Rectangle Selection	Rectangle selection tool.
 Intelligent Scissors	Intelligent Scissors selection tool.
 Intelligent Paint	Intelligent Paint selection tool.
 Magic Wand	Magic Wand selection tool.
 View Points	Shows detected features used for alignment of the current photo.
 Add Selection	Adds current selection to the mask.
 Subtract Selection	Subtracts current selection from the mask.
 Invert Selection	Inverts current selection.
Import Mask...	Imports masks or creates mask from alpha channel.
Export Mask...	Exports masks templates.
 Reset Mask...	Resets mask for the current photo.
 Turn Shading On/Off	Turns mask shading on or off.

Help Menu

 Contents	Displays help contents.
Check for Updates...	Checks if PhotoScan update is available for download.
Register Product...	Activates the product using the activation key.
 About PhotoScan...	Displays program information, version number and copyright.

Toolbar Buttons


General commands

 New	Creates a new PhotoScan project file.
 Open	Opens a PhotoScan project file.
 Save	Saves a PhotoScan project file.


3D view commands

 Navigation	Navigation tool.
 Rectangle Selection	Rectangle selection tool.


3D view commands

 Circle Selection


Circle selection tool.

 Resize region

Volume selection tool.

 Rotate Region

Volume rotation tool.

 Delete Selection

Removes selected faces / points.

 Crop Selection

Crops selected faces / points.


 Undo

Undo the last editing operation.

 Redo

Redo the previously undone editing operation.

3D view settings

 Point Cloud

Shows / hides sparse point cloud reconstructed during image alignment.

 Shaded

Displays 3D model in the shaded mode.

 Solid

Displays 3D model in the solid mode.

 Wireframe

Displays 3D model in the wireframe mode.

 Textured

Displays 3D model in the textured mode.

 Show Cameras

Shows / hides camera positions, reconstructed during image alignment.


 Show Aligned Chunks

Shows / hides aligned chunks.


 Reset View

Resets model view.


Photo view commands

 Navigation


Switches to the navigation mode.

 Rectangle Selection

Rectangle selection tool.

 Intelligent Scissors

Intelligent scissors tool.

 Intelligent Paint

Intelligent paint tool.

 Magic Wand


Magic wand tool.

 View Points

Shows / hides feature points used for alignment of the photo.

 Add Selection

Adds current selection to the mask.

 Subtract Selection

Subtracts current selection from the mask.

 Invert Selection

Inverts current selection.

 Undo

Undo the last mask editing operation.

Photo view commands



Redo

Redo the previously undone mask editing operation.



Rotate Right

Rotates the photo clockwise.



Rotate Left

Rotates the photo counterclockwise.



Zoom In

Increases magnification.



Zoom Out

Decreases magnification.



Turn Shading On/Off

Turns mask shading on or off.

Appendix B. Troubleshooting


Photo alignment succeeds, but the resulting camera positions appear to be wrong

The main reasons for the wrong photo alignment are listed below:

- Small overlap between the photos
- Object movement against the background scene
- Insufficient number of object surface details captured by the camera
- Strong blur or noise on the source photos

To obtain more information about the reason for alignment failure for the specific dataset it may be helpful to inspect feature points used for alignment of the photos as seen by the PhotoScan algorithms.

To inspect feature points used for alignment

1. Open the photo to be inspected by double-clicking on its name on the Workspace pane. The photo will be displayed in the main window.
2. Switch to the point view mode using  View Points toolbar button. The points used for alignment of the photo will be overlayed on the image.

Depending on the observed point placement the following recommendations may help to solve the problem:

Problem	Possible reason	Recommended solution
Not enough points were used.	Low image quality or too small photo overlap.	Try making better photos with a better camera placement. Pay attention to the camera settings, like proper level of ISO. Use a tripod if required. Setting a proper lighting may be also helpful to capture higher amount of surface details.
The majority of points used belong to the background objects.	The object was not static during capturing or occupies only a small area on the photos.	Mask out background regions or consider shooting another photo set so that the object spans significant area on the photos. If masking of the background areas is used, make sure that Constrain features by mask option in the Align Photos dialog box is checked.

Reconstructed geometry appears to be cut and some important parts are missing

Usually this indicates that a wrong reconstruction volume was selected. By default PhotoScan uses an automatic reconstruction volume selection algorithm, which can produce undesirable selections in some cases. All object parts outside of the selected reconstruction volume are cropped and are not included in


the final model. Too large reconstruction volume selections are also undesirable as they result in longer processing time and greater memory consumption.

To overcome this problem a manual reconstruction volume selection tool should be used.

Note

- The photos must be aligned before the reconstruction volume can be defined.

To select the reconstruction volume manually

1. Select the manual reconstruction volume selection tool using  Select Volume toolbar button.
2. Modify the displayed bounding box by dragging the corners of the box to the desired locations.
3. Before starting to reconstruct geometry make sure that Selection option is chosen from the Reconstruction volume drop down list.

The photos included in the project file can't be opened and operations from the Workflow menu fail

Probably the locations of photos have changed in respect to the location of the project file. The references to the original photos are stored in the project files in the form of relative paths. These references become invalid when the project file alone is moved to another location, or when the photos are moved without changing the project file placement.

To identify the expected photo location

1. Open the context menu of the photo by right-clicking on its title in the Workspace pane.
2. Select Show Info... command from the context menu.
3. A dialog box with information on the selected photo including the path to the image data file will be displayed.

To fix the problem move the photos to the original locations indicated by the data displayed in the information dialog box.

If the relative location of the project file in respect to the photos location must be changed, the project file should be resaved using the Save As... command from the File menu.

To move the project file in respect to the source photo locations

1. Open the project to be moved using Open... command from the File menu.
2. Select Save As... command from the File menu. Browse to the folder where the project file should be placed and specify the destination file name for the project. Click Save button to save the project.

Once the project file was saved to a new location, the original project file can be removed, if necessary.